



# East 4

## version 4.0.1 Installation Instructions

January 25, 2006

### **1. Single User License : Current user of East 4 (version 4.0)**

A. If installing as new software:

- a) Uninstall the current East 4 installation from "Start->Programs->East 4->Uninstall East 4". Then remove the East 4 installation folder completely, as the uninstallation process may not remove all the files from the folder. (Note: Please save your license files 'Iservrc' and 'East4Feature.info' in a separate folder convenient to you, before you start the uninstallation process. The 'Iservrc' is common to all the users, but the file 'East4Feature.info' will be required only if you have bought additional modules 'EastSurv' and 'EastAdapt')
- b) Insert the East 4 CD in your CDROM drive and follow the instructions that appear on the setup screen. If 'autorun' is not enabled in your computer, you will not get the setup screen automatically on the screen. In that case, click on 'setup.exe' on the CD, to get the setup screen.
- c) After the installation, copy the license files 'Iservrc' and 'East4Feature.info' into the East 4 installation folder.
- d) After successful installation, if you click on the menu item 'Help-About East", the version number will appear as 4.0.1.50 (Jan 23, 2006).
- e) You may refer to the files 'ReadMe.txt' and 'Bugs Fixed – East4.0.1.pdf", that you will find in the East 4 installation folder, for further useful information.

B. If installing as a Patch to the current installation

- a) Insert the CD containing Patch for East 4 in your CDROM drive. Click on the only file on the CD 'East4Patch1.exe'. This action will update the current installation of East 4.
- b) After successful installation, if you click on the menu item 'Help-About East", the version number will appear as 4.0.1.50 (Jan 23, 2006).

### **2. Single User License : New user of East 4**

Follow the steps for "Single User License : Current user of East 4 (version 4.0) : A. If installing as a new software)", excepting the uninstallation process.

### **3. Network License : Current user of East 4 (version 4.0)**

You need to carry out the installation process only on the client machines using the network CD. The process is similar to "Single User License : Current user of East 4 (version 4.0)"

### **4. Network License : New user of East 4**

The detailed instructions are in the file "Setup.doc" contained in the network CD.