

# East<sup>®</sup> 5.2

## East Upgrade - 5.1 to 5.2: Installation Instructions

April 15, 2008

**Note:** *These instructions explain how to upgrade from East 5.1 to East 5.2.*

- *If you are running East 5.0, you must first upgrade from East 5.0 to East 5.1. The patch and installation instructions can be found at [www.cytel.com](http://www.cytel.com) in the section "Support-Patches-East"*
- *If you are running an older version of East, you must install East 5.2 from the East 5.2 CD*
- *If you would like to run East 5.2 with Microsoft Excel 2007, you must install East 5.2 from the East 5.2 CD for Excel 2007*

### **1. Single User License: Current user of East 5 (version 5.1)**

#### **A. If installing as a new software:**

- Uninstall the current East 5 installation from "Start->Programs->East 5->Uninstall East 5". Then remove the East 5 installation folder completely, as the uninstallation process may not remove all the files from the folder. (**Note:** Please save your license files 'lservrc' and 'East5Feature.info' in a separate folder convenient to you, before you start the uninstallation process. The 'lservrc' is common to all the users, but the file 'East5Feature.info' will be required only if you have bought additional modules 'EastSurv', 'EastAdapt', and 'EastXact')
- Insert the East 5.2 CD in your CD drive and follow the instructions that appear on the setup screen. If 'autorun' is not enabled in your computer, you will not get the setup screen automatically on the screen. In that case, click on 'setup.exe' on the CD, to get the setup screen.
- After the installation, copy the license files 'lservrc' and 'East5Feature.info' into the East 5 installation folder.
- After successful installation, if you click on the menu item 'Help-About East...', the version number will appear as 5.2.0.0 (Apr 9, 2008).
- You may refer to the file 'ReadMe.txt', that you will find in the East 5 installation folder, for further useful information.

#### **B. If installing as an upgrade to the current installation**

- Perform one of the following actions:
  - Download 'East Upgrade - 5.1 to 5.2.zip' file from our website [www.cytel.com](http://www.cytel.com) in the section 'Support-Patches-East' and store it in a temporary folder. This zip file contains two items: A file 'East Upgrade - 5.1 to 5.2.exe' and a folder 'INSTVALDNFILES'. Double click on 'East Upgrade - 5.1 to 5.2.exe'. This action will upgrade the current installation of East 5.1 to 5.2. After this, delete the old folder 'INSTVALDNFILES' from your East installation folder and paste the new folder 'INSTVALDNFILES' in its place.

OR

ii) Insert the CD containing the file 'East Upgrade – 5.1 to 5.2.exe' and the folder 'INSTVALDNFILES' in your CD drive. Click on the file in the CD 'East Upgrade - 5.1 to 5.2.exe'. This action will upgrade the current installation of East 5.1 to 5.2. After this, delete the old folder 'INSTVALDNFILES' from your East installation folder and paste the new folder 'INSTVALDNFILES' in its place.

b) After successful installation, if you click on the menu item 'Help-About East...' the version number will appear as 5.2.0.0 (April 9, 2008).

***2. Single User License: New user of East 5***

Follow the steps for "Single User License: Current user of East 5 (version 5.1): A. If installing as a new software", excepting the uninstallation process.

***3. Network License: Current user of East 5 (version 5.1)***

You need to carry out the installation process only on the client machines using the network CD. The process is similar to "Single User License: Current user of East 5 (version 5.1)"

***4. Network License: New user of East 5***

The detailed instructions are in the file "Setup.doc" contained in the network CD